# AVR-SD Card Module Guide

Joshua Fain – 9/28/2020

## Table of Contents

Ta	ble of Contents	1-2
1.	INTRODUCTION	1-4
1	1.1 Overview	
2.	LISTS of OBJECTS, MACROS, and FUNCTIONS	2-7
2	2.1 FUNCTIONS	2-7
	SD_SPI_BASE	
	SD_SPI_DATA_ACCESS	
	SD_SPI_MISC	2-7
	2.2 OBJECTS	2-8
	SD SPI BASE	
,		
2	2.3 MACROS	
	SD_SPI_BASESD SPI DATA ACCESS	
<i>3</i> .	FUNCTION DETAILS	3-13
	3.1 SD SPI BASE	3-13
	uint32 t SD InitializeSPImode(CardTypeVersion *ctv)	
	void SD_SendByteSPI(uint8_t byte)	3-14
	uint8_t SD_ReceiveByteSPI(void)	
	void SD_SendCommand(uint8_t cmd, uint32_t arg)	
	uint8_t SD_GetR1(void)	
	void SD_PrintR1(uint8_t r1)	
	void SD_PrintInitError(uint32_t err)	3-16
	3.2 SD SPI DATA ACCESS	3-18
	uint16 t SD ReadSingleBlock(uint32 t blockAddress, uint8 t *block)	
	void SD_PrintSingleBlock(uint8_t *block)	
	uint16_t WriteSingleBlock(uint32_t blockAddress, uint8_t *data)	3-19
	uint16_t SD_EraseBlocks(uint32_t startBlockAdress, uint32_t endBlockAddress)	
	uint16_t SD_PrintMultipleBlocks(uint32_t startBlockAddress, uint32_t numberOfBlocks)	
	uint16_t SD_WriteMultipleBlocks(uint32_t startbBlockAddress, uint32_t numberOfBlocks, uint8_t 21	*data) 3-
	uint16 t SD GetNumberOfWellWrittenBlocks(uint32 t *wellWrittenBlocks)	3-22
	void SD_PrintReadError(uint16_t err)	
	void SD_PrintWriteError(uint16_t err)	
	void SD PrintEraseError(uint16 t err)	3-23

#### WARNINGS and DISCLAIMERS

- 1. **Use at your own risk**. This SD card module was developed for fun and so it is offered as is to anyone that wants to use it, look at it, or modify it for their needs. There is no guarantee of operability under any circumstance and it is possible to erase or overwrite data, lockout the SD card, and/or get the SD card into a bad logical or physical state. I take no responsibility for the loss of data or property through the use of this SD card module.
- 2. Backup Data! See 1.
- 3. This module has only been tested on an ATmega1280 microcontroller ( $\mu$ C). It is expected to be easily portable to other AVR  $\mu$ Cs through simple port (e.g. SPI, USART) reassignments, provided the resources exist, but also see 1.
- 4. This module has only been tested against version 2.x, 2GB and 4GB micro-SD cards of type SDSC (standard capacity) and SDHC (high capacity). It is unknown how it will behave running against other SD card types, versions, and capacities. Again, see 1.

#### 1. INTRODUCTION

The AVR-SDCard module has been developed to provide the ability to execute SPI mode SD card commands from an AVR target. The module can either be implemented as a standalone raw data access module, or as a physical disk layer in another application, e.g. operating underneath a file system layer. This document is intended to provide a brief overview of the structure of the module and then describe the functions, flags, and objects available for use.

#### 1.1 Overview

This SD Card module is divided into 3 separate source/header files:

- 1) SD SPI BASE basic functions required for interaction with the SD card.
- 2) SD SPI DATA ACCESS special functions that can handle data access (e.g. R/W/E).
- 3) SD SPI MISC some miscellaneous functions.

Only SD\_SPI\_BASE is required for interaction with the SD card. It includes the SD card initialization routine as well as the basic send command and receive byte functions. The functions defined in SD\_SPI\_DATA\_ACCESS are special functions related to data access, e.g. reading, writing, and erasing data blocks. SD\_SPI\_MISC is intended to be a catch-all for miscellaneous functions.

The following files are required in order for the module to function, and so they have been included with the module, however, they are not considered part of the module and so will not be discussed in detail here. These modules are maintained in the AVR-General repository.

- 1) SPI.C / SPI.H required to interface with the AVR's SPI port used for physical transmission and reception of byte-sized data packets.
- 2) USART.C / USART.H required to interface with the AVR's USART port used to print messages and data to a terminal.
- 3) PRINTS.C / PRINTS.H required to print integers (decimal, hex, binary) and strings to the screen via the USART.

#### Getting Started – Initialization

Any implementation of this module must first initialize the USART and SPI ports. Once these have been initialized, a new CardTypeVersion struct object must be created and passed, as a pointer, to the SD card initialization routine, SD\_InitializeSPImode(CardTypeVersion \*ctv) which will initialize the card into SPI mode. The initialization function will return an error response to indicate if initialization was successful or failed. This error response can then be read with the 'Print Error' functions to indicate if and where the routine failed. If the initialization was successful it will be in the OUT\_OF\_IDLE (0) state and it is then ready to proceed with calling other commands. The SD card initialization routine will also set the struct argument's *type* and *version* members.

NOTE: The initialization response is separated into an initialization error response and R1 response (more details later). Which can be printed using the SD\_PrintInitResponse() and SD\_PrintR1() functions, respectively.

#### *Initialization Example:*

The following example initializes the SD card and if successful it proceeds to execute a 'read block' and then a 'print block' function.

```
int main(void)
   USART Init();
   SPI MasterInit();
   CardTypeVersion ctv;
   uint32 initResponse;
   initResponse = SD InitializeSPImode(&ctv);
   if (((initResponse & 0xFF)!= OUT OF IDLE) &&
         (initResponse&0xFFF00) != 0)
   {
      //FAILED
      SD PrintR1(initResponse);
      SD PrintInitResponse(initResponse);
      //handle failed initialization
   }
   else // SUCCESSFULLY INITIALIZED
     // Simple read and print single block example.
     uint16 t err;
     Block bl;
     uint32 t blockNumber = 3;
     uint blockAddress;
     If (ctv.type == SDHC) blockAddress = blockNumber;
     Else blockAddress = blockNumber * BLOCK LEN;
     Err = SD ReadSingleBlock(blockAddress, &bl);
     SD PrintReadError(err);
     SD PrintDataBlock(bl.byte);
}
```

## Some details to keep in mind

1) A standard capacity card (SDSC) is byte addressable. A high capacity card (SDHC / SDXC) is block addressable. This means that when calling a block access function, such as SD\_ReadSingleBlock(addr, \*block), the address passed as argument 1 for type SDHC should be the block number, whereas for type SDSC the address should be the block number multiplied by the BLOCK\_LENGTH (i.e. the number of bytes in a block which should be 512).

## 2. LISTS of OBJECTS, MACROS, and FUNCTIONS

## 2.1 FUNCTIONS

SD\_SPI\_BASE

<u>RETURN</u>	<u>FUNCTION</u>
<b>TYPE</b>	
uint32_t	SD_InitializeSPImode(CardTypeVersion *ctv)
void	SD_SendByteSPI(uint8_t byte)
uint8_t	SD_ReceiveByteSPI(void)
void	SD_SendCommand(uint8_t cmd, uint32_t arg)
uint8_t	SD_GetR1(void)
void	SD_PrintR1(uint8_t r1)
void	SD_PrintInitError(uint32_t err)

## SD\_SPI\_DATA\_ACCESS

<b>RETURN</b>	<b>FUNCTION</b>
<b>TYPE</b>	
uint16_t	SD_ReadSingleBlock(uint32_t blockAddress, uint8_t *block)
void	SD_PrintSingleBlock(uint8_t *block)
uint16_t	SD_WriteSingleBlock(uint32_t blockAddress, uint8_t *data)
uint16_t	SD_EraseBlocks(uint32_t startBlockAddress, uint32_t endBlockAddress)
uint16_t	SD_PrintMultipleBlocks(uint32_t startBlockAddress, uint32_t
	numberOfBlocks)
uint16_t	SD_WriteMultipleBlocks(uint32_t startBlockAddress, uint32_t
	numberOfBlocks, uint8_t *data)
uint16_t	SD_GetNumberOfWellWrittenBlocks(uint32_t *wellWrittenBlocks)
void	SD_PrintReadError(uint16_t err)
void	SD_PrintWriteErrors(uint16_t err)
void	SD_PrintEraseError(uint16_t err)

## SD\_SPI\_MISC

<u>RETURN</u>	<u>FUNCTION</u>
<b>TYPE</b>	
uint32_t	SD_GetMemoryCapacity(void)
void	SD PrintNonZeroBlockNumbers(uint32 t startBlock, uint32 t endBlock)

## 2.2 OBJECTS

## SD\_SPI\_BASE

TYPE KIND CardTypeVersion typedef struct

## 2.3 MACROS

SD\_SPI\_BASE

## SPI\_Mode SD Card Commands

COMMAND	<b>VALUE</b>
GO_IDLE_STATE	0
SEND_OP_COND	1
SWITCH_FUNC	6
SEND_IF_COND	8
SEND_CSD	9
SEND_CID	10
STOP_TRANSMISSION	12
SEND_STATUS	13
SET_BLOCKLEN	16
READ_SINGLE_BLOCK	17
READ_MULTIPLE_BLOCK	18
WRITE_BLOCK	24
WRITE_MULTIPLE_BLOCK	25
PROGRAM_CSD	27
SET_WRITE_PROT	28
CLR_WRITE_PROT	29
SEND_WRITE_PROT	30
ERASE_WR_BLK_START_ADDR	32
ERASE_WR_BLK_END_ADDR	33
ERASE	38
LOCK_UNLOCK	42
APP_CMD	55
GEN_CMD	56
READ_OCR	58
CRC_ON_OFF	59

## **Application Specific Command**

Must call command APP\_CMD prior to calling any of these App Commands

APP COMMAND	<b>VALUE</b>
SD_STATUS	13
SEND_NUM_WR_BLOCKS	22
SET_WR_BLK_ERASE_COUNT	23
SD_SEND_OP_COND	41
SET_CLR_CARD_DETECT	42
SEND_SCR	51

## Card Types - Standard or High Capacity

Card Type	<b>VALUE</b>
SDSC	0
SDHC	1

## Assert / De-assert CS

CS is the SD card's pin connected to the SS pin of the SPI port. When CS is asserted it signals to the card to prepare for a command. De-asserting stops communication with the SD card.

CS STATE	<b>ACTION</b>
CS_LOW	Asserts CS
CS_HIGH	De-asserts CS

### R1 Response Flags

An R1 response is the first byte returned by an SD card in response to any command. With the exception of OUT\_OF\_IDLE and R1\_TIMEOUT, the values of these flags are the SD card's R1 responses. Use  $SD\_GetR1()$  to get the R1 response after sending a command, and SD\_PrintR1() to read response.

- OUT\_OF\_IDLE is defined here to be the state when no flags are set in the SD card's R1 response (i.e. No errors are returned in R1 and the card is not IN\_IDLE\_STATE).
- R1\_TIMEOUT: bit 7 of an SD card's R1 response is reserved (always 0). The SD\_GetR1() makes use of this bit by indicating a timeout waiting for the R1 response.

R1 FLAGS	<b>VALUE</b>
OUT_OF_IDLE	0x00
IN_IDLE_STATE	0x01
ERASE_RESET	0x02
ILLEGAL_COMMAND	0x04
COM_CRC_ERROR	0x08
ERASE_SEQUENCE_ERROR	0x10
ADDRESS_ERROR	0x20
PARAMETER_ERROR	0x40
R1_TIMEOUT	0x80

#### **Initialization Error Flags**

Initialization error flags are returned in bits 8 to 16 of SD\_InitializationSPImode() 's returned value the lowest byte is set to zero to accommodate the R1 portion of the response. Use SD\_PrintInitError() to read the initialization error flags.

<b>INITIALIZATION ERROR</b>	<b>VALUE</b>
FLAGS	
FAILED_GO_IDLE_STATE	0x00100
FAILED_SEND_IF_COND	0x00200
UNSUPPORTED_CARD_TYPE	0x00400
FAILED_CRC_ON_OFF	0x00800
FAILED_APP_CMD	0x01000
FAILED_SD_SEND_OP_COND	0x02000
OUT_OF_IDLE_TIMEOUT	0x04000
FAILED_READ_OCR	0x08000
POWER_UP_NOT_COMPLETE	0x10000

## High Capacity Support

Set to 1 if the host should support high capacity cards (SDHC / SDXC). Set to 0 if host should only support standard capacity cards (SDSC).

### MACRO DEFAULT VALUE

HCS 1

## Block Length

Defines the expected length, in bytes, of an SD card block. This value should always be 512. No other values for this have been tested, and changing this will likely make the module unusable.

MACRO DEFAULT

**VALUE** 

BLOCK\_LENGTH 512

## Read Error Flags

Flags returned by *Read Block* commands in SD\_SPI\_DATA\_ACCESS. The lowest byte is 0 to accommodate the R1 portion of the response.

READ ERROR FLAGS	<b>VALUE</b>
START_TOKEN_TIMEOUT	0x0200
READ_SUCCESS	0x0400

## Write Error Flags

Flags returned by *Write Block* commands in SD\_SPI\_DATA\_ACCESS. The lowest byte is 0 to accommodate the R1 portion of the response.

WRITE ERROR FLAGS	<b>VALUE</b>
DATA_ACCEPTED_TOKEN	0x00100
CRC_ERROR_TOKEN	0x00200
WRITE_ERROR_TOKEN	0x00400
INVALID_DATA_RESPONSE	0x00800
DATA_RESPONSE_TIMEOUT	0x01000
CARD_BUSY_TIMEOUT	0x02000

### Erase Error Flags

Flags returned by *Write Block* commands in SD\_SPI\_DATA\_ACCESS. The lowest byte is 0 to accommodate the R1 portion of the response.

ERASE ERROR FLAGS	<b>VALUE</b>
ERASE_SUCCESSFUL	0x00100
SET_ERASE_START_ADDR_ERROR	0x00200
SET_ERASE_END_ADDR_ERROR	0x00400
ERROR_ERASE	0x00800
ERASE_BUSY_TIMEOUT	0x01000

#### R1 Error Flag

This flag is used by function in SD\_SPI\_DATA\_ACCESS to indicate the returned value is an R1 an R1 response.

Error Flag R1 ERROR 0x8000

#### 3. FUNCTION DETAILS

### 3.1 SD SPI BASE

uint32 t SD InitializeSPImode(CardTypeVersion \*ctv)

#### DESCRIPTION

Initializes an SD card into SPI mode. It also determines the SD card's type and version and sets the CardTypeVersion stuct object's members accordingly. Only this function should set the CardTypeVersion members and once set they should not be changed. The SD card is successfully initialized if INIT\_SUCCESS and OUT\_OF\_IDLE are the initialization error and R1 portions of the initialization reponse, respectively.

#### **ARGUMENT**

Pointer to CardTypeVersion struct

The struct object's members will be set by this function according to the card's type and version.

#### **RETURNS**

uint32 t

The returned value is the initialization response and is divided into two portions:

#### *Initialization Error Response* [8:16]

This portion of the response occupies bits 8 to 16 of the returned value, and corresponds to the *Initialization Error Flags*. Pass the returned value to *SD\_PrintInitResponse()* to read this portion of the response

#### *R1 Response* [0:7]

This portion of the response occupies the lowest byte (bits 0 to 7) of the returned value, and correspond to the R1 Response Flags. This represents the most recently returned R1 response from the SD card retrieved using the SD\_GetR1() during the initialization function. Use SD\_PrintR1() to print the R1 portion of the response.

NOTE: bits 17 to 31 in the returned value are currently not used and should be 0.

#### **EXAMPLE**

```
CardTypeVersion ctv;
uint32_t err = SD_InitializeSPImode(CardTypeVersion *cvt);
SD_PrintR1(err);
SD_PrintInitError(err);
```

void SD\_SendByteSPI(uint8\_t byte)

#### **DESCRIPTION**

Sends a single byte to the SD card via SPI. This function, along with SD\_ReceiveByteSPI() are the SPI interfacing functions. This function is used by SD\_SendCommand() to send the command / argument in byte sized packets to the SD card.

#### **ARGUMENTS**

uint8\_t

The next byte to be sent to the SD card.

#### **RETURNS**

none

uint8\_t SD\_ReceiveByteSPI(void)

#### **DESCRIPTION**

Gets the next byte returned by the SD card via SPI. This function, along with SD\_SendByteSPI() are the SPI interfacing functions.

#### **ARGUMENT**

none

#### **RETURN**

uint8 t

The next byte returned by the SD card.

void SD\_SendCommand(uint8\_t cmd, uint32\_t arg)

#### **DESCRIPTION**

Sends an SD card command, argument to the SD card.

#### **ARGUMENTS**

(1) *uint8\_t* 

A valid SPI mode SD card command (cmd) from the list.

(2) uint32 t

The argument (arg) to be sent with the command.

#### **RETURNS**

none

#### **NOTE**

This function also sends a valid CRC7 token to the SD card. The CRC7 token is generated by calling a "private" function, however, in this current version, the CRC value does not matter (except for CMD0), as the CRC check is turned off (default). It should not be turned on because handling of other CRC values (e.g. on write) is currently not supported.

uint8\_t SD\_GetR1(void)

#### **DESCRIPTION**

Gets the R1 response returned by an SD card for a given command / argument. This function should be called immediately after SD\_SendCommand() to get the R1 response.

#### **ARGUMENT**

none

#### **RETURNS**

uint8 t

The R1 response byte returned by the SD card to a given command. This function will only return a valid response if it is called immediately after a command has been sent to the SD card. If any other function queries the SPI Data Register (SPDR) after sending a command, then the R1 response returned by this function will be may not correspond to the actual R1 response. Call SD PrintR1() to print the returned value.

void SD\_PrintR1(uint8\_t r1)

**DESCRIPTION:** 

Prints the R1 response returned by SD GetR1()

ARGUMENT:

uint8 t

The R1 byte response returned by SD GetR1().

#### **RETURN**

none

#### **NOTES**

The actual SD card's R1 response occupies bits 0 to 6 of the first byte returned by an SD card in SPI mode; bit 7 is reserved and should be 0 when returned by the SD card. The function, SD\_GetR1(), however, uses bit 7 as the R1\_TIMEOUT flag to indicate the SD card did not return a response within an acceptable amount of time or number of attempts. If R1 response is 0, then the card is not in idle and no errors were returned in the R1 response. In this case OUT\_OF\_IDLE state will be the 'value' of the R1 response. During initialization, the card should be in the idle state and no error means only the IN\_IDLE\_STATE flag is set.

void SD\_PrintInitError(uint32\_t err)

#### DESCRIPTION

Prints the initialization error response flags returned by SD\_InitializeSPImode(). This function does not print the R1 response portion of the initialization response.

**ARGUMENT** 

uint32 t

The Initialization Error Response portion of the initialization routine's [SD\_InitializeSPImode()] returned value. This function will filter out the R1 portion of the response, so passing the entire 32-bit returned value of the initialization routine is valid.

### **RETURNS**

none

#### **NOTES**

The R1 portion SD\_InitializeSPImode() portion of the response should be passed to SD\_PrintR1() in order to read it's values.

## 3.2 SD SPI DATA ACCESS

uint16 t SD ReadSingleBlock(uint32 t blockAddress, uint8 t \*block)

#### **DESCRIPTION**

Reads in a single 512-byte block from the SD card from location 'blockAddress', and stores the contents of the block in the array pointed at by '\*block'.

#### **ARGUMENTS**

(1) uint32 t blockAddress

The address on the SD card of the block to be read. A single block in this implementation is always 512 bytes (value of BLOCK\_LEN). If the card is SDSC then the card is byte addressable. If the card is SDHC/SDXC then the card is block addressable.

(2) *uint8 t* \**block* 

A pointer to a *uint8\_t* array of length 512 (BLOCK\_LEN). The function will update the contents of the array with the values of the single byte block at the address specified by argument 1.

#### **RETURNS**

uint16 t

Read Block Error Response. This response is composed of the *Read Block Error Flags* in the upper byte, and the R1 response returned after sending the READ\_SINGLE\_BLOCK command in the lower byte. Read the *Read Block Error Flags* returned using SD\_PrintReadError(err). If the R1\_ERROR flag is set in the upper portion of the response, then an R1 error occurred. The R1 portion can be read by using SD\_PrintR1(R1).

void SD PrintSingleBlock(uint8 t \*block)

#### DESCRIPTION

This function should be used in conjunction with SD\_ReadSingleBlock() to print the contents of the block that was read in by that function. The contents must be stored in the 512-byte length array pointed at by the argument.

This function prints the hexadecimal and ASCII characters of the block's contents in rows of 16-bytes. The beginning of each row is the byte offset of the first byte of the row.

#### **ARGUMENT**

uint8 t \*block

A pointer to a *uint8\_t array* of length 512 (BLOCK\_LEN) that contains the contents of an SD card block stored in the array by the SD ReadSingleBlock() function.

#### **RETURNS**

none

uint16\_t WriteSingleBlock(uint32\_t blockAddress, uint8\_t \*data)

#### **DESCRIPTION**

Writes data to a single block on the SD card.

#### **ARGUMENTS**

(1) uint32 t blockAddress

The address on the SD card of the block to write the data to. A single block in this implementation is always 512 bytes (value of BLOCK\_LEN). If the card is SDSC then the card is byte addressable. If the card is SDHC/SDXC then the card is block addressable.

(2) *uint8 t* \**data* 

A pointer to a *uint8\_t* array of length 512 (BLOCK\_LEN) that contains the contents of the data to write to the SD card.

#### **RETURNS**

uint16 t

Write Block Error Response. This response is composed of the *Write Block Error Flags* in the upper byte, and the R1 response returned after sending the WRITE\_BLOCK command in the lower byte. Read the *Write Block Error Flags* returned by using SD\_PrintWriteError(err). If the R1\_ERROR flag is set in the upper portion of the response, then an R1 error occurred. The R1 portion can be read by using SD\_PrintR1(R1).

uint16\_t SD\_EraseBlocks(uint32\_t startBlockAdress, uint32\_t endBlockAddress)

#### DESCRIPTION

Erases the blocks between, and including, startBlockAdress and endBlockAddress.

#### **ARGUMENTS**

(1) *uint32 t startBlockAddress* 

The address of the first block that will be erased. If the card is SDSC then the card is byte addressable. If the card is SDHC/SDXC then the card is block addressable.

(2) *uint32* t endBlockAddress

The address of the last block that will be erased, and must be greater than the start address. If the card is SDSC then the card is byte addressable. If the card is SDHC/SDXC then the card is block addressable.

#### **RETURNS**

uint16 t

Erase Error Response. This response is composed of the Erase Error Flags in the upper byte, and returned after required the R1 response sending on of the commands (ERASE WR BLK START ADDR, ERASE WR BLK END ADDR, or ERASE) in the lower byte. Read the Erase Error Flags returned by using SD PrintEraseError(err). If the R1 ERROR flag is set in the upper portion of the response, then an R1 error occurred. The R1 portion can be read by using SD PrintR1(R1).

uint16\_t SD\_PrintMultipleBlocks(uint32\_t startBlockAddress, uint32\_t numberOfBlocks)

#### DESCRIPTION

Prints the contents of a specified number of consecutive blocks from the SD card beginning at start block address. This function operates by sending the READ\_MULTIPLE\_BLOCK command and then calling the SD\_PrintSingleBlock() function to print a block's contents every time a new block is returned by the SD card, until all the specified blocks have been read in.

#### **ARGUMENTS**

(1) uint32 t startBlockAddress

The address of the first block to print. If the card is SDSC then the card is byte addressable. If the card is SDHC/SDXC then the card is block addressable.

(2) *uint32\_t numberOfBlocks* 

The number of blocks to print to the screen, beginning at startBlockAddress.

#### **RETURNS**

Read Block Error Response. This response is composed of the *Read Block Error Flags* in the upper byte, and the R1 response returned after sending the READ\_MULTIPLE\_BLOCK command in the lower byte. Read the *Read Block Error Flags* returned using SD\_PrintReadError(err). If the R1\_ERROR flag is set in the upper portion of the response, then an R1 error occurred. The R1 portion can be read by using SD\_PrintR1(R1).

uint16\_t SD\_WriteMultipleBlocks(uint32\_t startbBlockAddress, uint32\_t numberOfBlocks, uint8\_t \*data)

#### DESCRIPTION

Writes the contents of the array pointed at by \*data to multiple consecutive blocks. This function is not that useful as it writes the same data to multiple blocks, but it is mainly intended to be a demo of the WRITE\_MULTIPLE\_BLOCK command.

#### **ARGUMENTS**

(1) uint32 t startBlockAddress

The address of the first block that will be written to. If the card is SDSC then the card is byte addressable. If the card is SDHC/SDXC then the card is block addressable.

(2) uint32 t numberOfBlocks

Specifies the total number of blocks that will be written to.

(3) uint8 t\*data

Pointer to a uint8\_t array of length 512 (BLOCK\_LEN) that contains the data that will be written to the blocks.

#### **RETURNS**

Write Block Error Response. This response is composed of the *Write Block Error Flags* in the upper byte, and the R1 response returned after sending the WRITE\_MULTIPLE\_BLOCK command in the lower byte. Read the *Write Block Error Flags* returned by using SD\_PrintWriteError(err). If the R1\_ERROR flag is set in the upper portion of the response, then an R1 error occurred. The R1 portion can be read by using SD\_PrintR1(R1).

uint16\_t SD\_GetNumberOfWellWrittenBlocks(uint32\_t \*wellWrittenBlocks)

#### **DESCRIPTION**

This function should be called if the WRITE\_ERROR\_TOKEN was returned by the SD card while carrying out the WRITE\_MULTIPLE\_BLOCK command. If this token was returned by the card when calling the function SD\_WriteMultipleBlocks() then the WRITE\_ERROR\_TOKEN\_FLAG will be set in its return response, in which case this function should be called.

#### **ARGUMENT**

uint32 t \*wellWrittenBlocks

Pointer to a value of type uint32\_t that will be updated with the value of the number of well written blocks returned by the SD card after upon sending the SEND\_NUM\_WR\_BLOCKS (ACMD22).

#### **RETURNS**

This function executes similarly to a read block function so it will return a Read Block Error Response. This response is composed of the *Read Block Error Flags* in the upper byte, and the R1 response returned after sending APP\_CMD or SEND\_NUM\_WR\_BLOCKS commands in the lower byte. Read the *Read Block Error Flags* returned using SD\_PrintReadError(err). If the R1\_ERROR flag is set in the upper portion of the response, then an R1 error occurred. The R1 portion can be read by using SD\_PrintR1(R1).

void SD\_PrintReadError(uint16\_t err)

#### **DESCRIPTION**

Prints Read Block Error Flags

#### **ARGUMENT**

uint16\_t err

Read Block Error Response

#### **RETURNS**

none

void SD\_PrintWriteError(uint16\_t err)

#### **DESCRIPTION**

Prints Write Block Error Flags

#### **ARGUMENT**

uint16\_t err

Write Block Error Response

#### **RETURNS**

none

void SD\_PrintEraseError(uint16\_t err)

#### **DESCRIPTION**

Prints Erase Error Flags

#### **ARGUMENT**

uint16\_t err

Erase Error Response

## **RETURNS**

none